

JIS04字形とJIS90字形のIVS

No.	区点	04字形	Unicode	VS	04字形 CID	90字形	Unicode	VS	90字形 CID
1	1609	逢	U+9022	E0101	8266	逢	U+9022	E0100	1133
2	1618	芦	U+82A6	E0101	7961	芦	U+82A6	E0100	1142
3	1627	飴	U+98F4	E0101	7634	飴	U+98F4	E0100	1151
4	1678	溢	U+6EA2	E0101	7635	溢	U+6EA2	E0100	1202
5	1681	茨	U+8328	E0101	7962	茨	U+8328	E0100	1205
6	1683	鰯	U+9C2F	E0101	7636	鰯	U+9C2F	E0100	1207
7	1692	淫	U+6DEB	E0101	7637	淫	U+6DEB	E0100	1216
8	1710	迂	U+8FC2	E0101	7638	迂	U+8FC2	E0100	1228
9	1725	厩	U+53A9	E0105	20271	厩	U+53A9	E0100	1243
10	1729	樽	U+5642	E0101	7642	樽	U+5642	E0100	1247
11	1734	餌	U+990C	E0103	13650	餌	U+990C	E0100	1252
12	1808	襖	U+8956	E0101	7645	襖	U+8956	E0100	1320
13	1864	迦	U+8FE6	E0101	7647	迦	U+8FE6	E0100	1376
14	1871	牙	U+7259	E0101	7965	牙	U+7259	E0100	1383
15	1886	廻	U+5EFB	E0101	13673	廻	U+5EFB	E0100	1398
16	1890	恢	U+6062	E0102	20269	恢	U+6062	E0100	1402
17	1902	晦	U+6666	E0101	7650	晦	U+6666	E0100	1408
18	1910	蟹	U+87F9	E0100	1416	一	—	—	—
19	1975	葛	U+845B	E0101	7652	葛	U+845B	E0100	1481
20	1983	鞆	U+9784	E0101	7653	鞆	U+9784	E0100	1489
21	1988	釜	U+91DC	E0101	20290	釜	U+91DC	E0100	1494
22	2045	翰	U+7FF0	E0101	7656	翰	U+7FF0	E0100	1545
23	2069	翫	U+7FEB	E0101	7657	翫	U+7FEB	E0100	1569
24	2111	徽	U+5FBD	E0101	7658	徽	U+5FBD	E0100	1605
25	2132	祇	U+7947	E0101	7659	祇	U+7947	E0100	1626
26	2166	汲	U+6C72	E0101	7966	汲	U+6C72	E0100	1660
27	2168	灸	U+7078	E0101	20270	灸	U+7078	E0100	1662
28	2172	笈	U+7B08	E0102	20263	笈	U+7B08	E0100	1666
29	2210	卿	U+537F	E0102	7661	卿	U+537F	E0101	1698
30	2234	饗	U+9957	E0101	7968	饗	U+9957	E0100	1722

No.	区点	04字形	Unicode	VS	04字形 CID	90字形	Unicode	VS	90字形 CID
31	2247	僅	U+50C5	E0101	7662	僅	U+50C5	E0100	1735
32	2284	喰	U+55B0	E0101	7664	喰	U+55B0	E0100	1772
33	2291	櫛	U+6ADB	E0100	7665	櫛	U+6ADB	E0101	1779
34	2293	屑	U+5C51	E0101	7666	屑	U+5C51	E0100	1781
35	2309	彖	U+7C82	E0101	20272	彖	U+7C82	E0100	1791
36	2323	邗	U+7941	E0101	7668	邗	U+7941	E0100	1805
37	2368	隙	U+9699	E0101	20273	隙	U+9699	E0100	1850
38	2381	倦	U+5026	E0101	7674	倦	U+5026	E0100	1863
39	2394	捲	U+6372	E0101	7676	捲	U+6372	E0100	1876
40	2403	牽	U+727D	E0100	1879	一	—	—	—
41	2416	鍵	U+9375	E0101	20276	鍵	U+9375	E0100	1892
42	2433	諺	U+8AFA	E0101	7678	諺	U+8AFA	E0100	1909
43	2511	巷	U+5DF7	E0101	7679	巷	U+5DF7	E0100	1981
44	2528	梗	U+6897	E0101	20279	梗	U+6897	E0100	1998
45	2549	膏	U+818F	E0100	2019	一	—	—	—
46	2584	鵠	U+9D60	E0101	7683	鵠	U+9D60	E0100	2054
47	2589	甌	U+7511	E0103	20284	甌	U+7511	E0100	2059
48	2621	叉	U+53C9	E0101	20281	叉	U+53C9	E0100	2085
49	2671	桫	U+698A	E0101	7686	桫	U+698A	E0100	2135
50	2707	薩	U+85A9	E0101	7688	薩	U+85A9	E0100	2165
51	2710	鯖	U+9BD6	E0101	7689	鯖	U+9BD6	E0100	2168
52	2712	鯖	U+9306	E0101	7690	鯖	U+9306	E0100	2170
53	2713	鮫	U+9BAB	E0101	20280	鮫	U+9BAB	E0100	2171
54	2733	餐	U+9910	E0101	7970	餐	U+9910	E0100	2191
55	2861	杓	U+6753	E0101	7695	杓	U+6753	E0100	2313
56	2862	灼	U+707C	E0101	7696	灼	U+707C	E0100	2314
57	2922	酋	U+914B	E0101	7698	酋	U+914B	E0100	2368
58	2961	楯	U+696F	E0101	13460	楯	U+696F	E0100	2407
59	2982	薯	U+85AF	E0101	7701	薯	U+85AF	E0100	2428
60	2983	諸	U+85F7	E0101	7702	諸	U+85F7	E0100	2429
61	3005	哨	U+54E8	E0101	7703	哨	U+54E8	E0100	2445

No.	区点	04字形	Unicode	VS	04字形 CID	90字形	Unicode	VS	90字形 CID
62	3068	鞘	U+9798	E0101	7708	鞘	U+9798	E0100	2508
63	3083	杖	U+6756	E0101	20282	杖	U+6756	E0100	2523
64	3110	蝕	U+8755	E0101	7709	蝕	U+8755	E0100	2544
65	3154	訊	U+8A0A	E0101	13860	訊	U+8A0A	E0100	2588
66	3164	逗	U+9017	E0101	7711	逗	U+9017	E0100	2598
67	3202	摺	U+647A	E0101	7713	摺	U+647A	E0100	2630
68	3281	撰	U+64B0	E0101	7716	撰	U+64B0	E0100	2709
69	3289	煎	U+714E	E0101	7718	煎	U+714E	E0100	2717
70	3290	煽	U+717D	E0102	7972	煽	U+717D	E0100	2718
71	3292	穿	U+7A7F	E0101	7973	穿	U+7A7F	E0100	2720
72	3293	箭	U+7BAD	E0101	7974	箭	U+7BAD	E0100	2721
73	3307	詮	U+8A6E	E0101	7720	詮	U+8A6E	E0100	2729
74	3325	噌	U+564C	E0101	7721	噌	U+564C	E0100	2747
75	3344	遡	U+9061	E0101	7722	遡	U+9061	E0100	2766
76	3423	揃	U+63C3	E0101	7975	揃	U+63C3	E0100	2839
77	3429	遜	U+905C	E0101	7726	遜	U+905C	E0100	2845
78	3460	腿	U+817F	E0101	7728	腿	U+817F	E0100	2876
79	3493	蛸	U+86F8	E0101	7733	蛸	U+86F8	E0100	2909
80	3509	辿	U+8FBF	E0101	7735	辿	U+8FBF	E0100	2919
81	3514	樽	U+6A3D	E0101	7738	樽	U+6A3D	E0100	2924
82	3523	歎	U+6B4E	E0101	13915	歎	U+6B4E	E0100	2933
83	3580	註	U+8A3B	E0101	7740	註	U+8A3B	E0100	2990
84	3585	瀦	U+7026	E0101	7741	瀦	U+7026	E0100	2995
85	3629	抄	U+6357	E0101	7743	抄	U+6357	E0100	3033
86	3640	槌	U+69CC	E0101	7744	槌	U+69CC	E0100	3044
87	3642	鎚	U+939A	E0101	7745	鎚	U+939A	E0100	3046
88	3652	辻	U+8FBB	E0101	8267	辻	U+8FBB	E0100	3056
89	3682	挺	U+633A	E0101	20286	挺	U+633A	E0100	3086
90	3702	鄭	U+912D	E0101	7748	鄭	U+912D	E0100	3100
91	3707	擢	U+64E2	E0101	7749	擢	U+64E2	E0100	3105
92	3714	溺	U+6EBA	E0101	7750	溺	U+6EBA	E0100	3112

No.	区点	04字形	Unicode	VS	04字形 CID	90字形	Unicode	VS	90字形 CID
93	3738	兔	U+514E	E0101	13949	兔	U+514E	E0100	3136
94	3740	堵	U+5835	E0101	7753	堵	U+5835	E0100	3138
95	3743	屠	U+5C60	E0101	7754	屠	U+5C60	E0100	3141
96	3750	賭	U+8CED	E0101	7756	賭	U+8CED	E0100	3148
97	3852	澗	U+701E	E0101	7761	澗	U+701E	E0100	3244
98	3859	遁	U+9041	E0102	20287	遁	U+9041	E0100	3251
99	3870	謎	U+8B0E	E0101	7766	謎	U+8B0E	E0100	3262
100	3871	灘	U+7058	E0101	7767	灘	U+7058	E0100	3263
101	3874	檣	U+6962	E0101	7768	檣	U+6962	E0100	3266
102	3909	禰	U+79B0	E0101	7769	禰	U+79B0	E0100	3295
103	3955	牌	U+724C	E0101	7771	牌	U+724C	E0100	3341
104	3971	這	U+9019	E0101	7772	這	U+9019	E0100	3357
105	3973	秤	U+79E4	E0101	7773	秤	U+79E4	E0100	3359
106	3993	駁	U+99C1	E0101	20288	駁	U+99C1	E0100	3379
107	4004	箸	U+7BB8	E0101	7775	箸	U+7BB8	E0100	3384
108	4032	叛	U+53DB	E0101	7978	叛	U+53DB	E0100	3412
109	4052	挽	U+633D	E0101	7778	挽	U+633D	E0100	3432
110	4080	誹	U+8AB9	E0101	13495	誹	U+8AB9	E0100	3460
111	4085	樋	U+6A0B	E0101	7780	樋	U+6A0B	E0100	3465
112	4103	稗	U+7A17	E0101	7782	稗	U+7A17	E0100	3477
113	4115	逼	U+903C	E0101	7783	逼	U+903C	E0100	3489
114	4121	謬	U+8B2C	E0101	7785	謬	U+8B2C	E0100	3495
115	4131	豹	U+8C79	E0101	20222	豹	U+8C79	E0100	3505
116	4132	廟	U+5EDF	E0101	7786	廟	U+5EDF	E0100	3506
117	4146	瀕	U+7015	E0101	7787	瀕	U+7015	E0100	3520
118	4164	斧	U+65A7	E0101	20289	斧	U+65A7	E0100	3538
119	4235	蔽	U+853D	E0101	7789	蔽	U+853D	E0100	3603
120	4245	瞥	U+77A5	E0101	7790	瞥	U+77A5	E0100	3613
121	4246	蔑	U+8511	E0101	14013	蔑	U+8511	E0100	3614
122	4251	篇	U+7BC7	E0101	7979	篇	U+7BC7	E0100	3619
123	4258	娩	U+5A29	E0101	7791	娩	U+5A29	E0100	3626

No.	区点	04字形	Unicode	VS	04字形 CID	90字形	Unicode	VS	90字形 CID
124	4260	鞭	U+97AD	E0101	20291	鞭	U+97AD	E0100	3628
125	4289	庖	U+5E96	E0101	7792	庖	U+5E96	E0100	3657
126	4309	蓬	U+84EC	E0101	7794	蓬	U+84EC	E0100	3671
127	4380	鱒	U+9C52	E0101	7796	鱒	U+9C52	E0100	3742
128	4388	迄	U+8FC4	E0101	7980	迄	U+8FC4	E0100	3750
129	4457	儲	U+5132	E0101	7798	儲	U+5132	E0100	3813
130	4463	餅	U+9905	E0101	7799	餅	U+9905	E0100	3819
131	4466	粩	U+7C7E	E0102	20293	粩	U+7C7E	E0100	3822
132	4476	爺	U+723A	E0101	20294	爺	U+723A	E0100	3832
133	4490	鎗	U+9453	E0101	7801	鎗	U+9453	E0100	3846
134	4492	愈	U+6108	E0101	7802	愈	U+6108	E0100	3848
135	4518	猷	U+7337	E0102	14074	猷	U+7337	E0100	3868
136	4690	漣	U+6F23	E0100	7809	漣	U+6F23	E0101	4034
137	4691	煉	U+7149	E0100	7810	煉	U+7149	E0101	4035
138	4692	簾	U+7C3E	E0102	20265	簾	U+7C3E	E0100	4036
139	4717	榔	U+6994	E0101	7812	榔	U+6994	E0100	4055
140	4764	屢	U+5C62	E0100	7693	一	—	—	—
141	4945	冤	U+51A4	E0101	7817	冤	U+51A4	E0100	4228
142	5055	叟	U+53DF	E0101	14111	叟	U+53DF	E0100	4332
143	5091	咬	U+54AC	E0101	20277	咬	U+54AC	E0100	4368
144	5162	嘲	U+5632	E0101	7821	嘲	U+5632	E0100	4433
145	5183	囀	U+56C0	E0101	14116	囀	U+56C0	E0100	4454
146	5549	徘	U+5F98	E0101	13538	徘	U+5F98	E0100	4796
147	5708	扁	U+6241	E0101	7991	扁	U+6241	E0100	4943
148	5989	棘	U+68D8	E0100	5212	一	—	—	—
149	6084	橙	U+6A59	E0100	5301	一	—	—	—
150	6436	狡	U+72E1	E0101	20278	狡	U+72E1	E0100	5629
151	6517	甕	U+7515	E0102	20267	甕	U+7515	E0100	5704
152	6520	甦	U+7526	E0101	20283	甦	U+7526	E0100	5707
153	6554	疼	U+75BC	E0101	20175	疼	U+75BC	E0100	5741
154	6714	崇	U+795F	E0100	5889	一	—	—	—

No.	区点	04字形	Unicode	VS	04字形 CID	90字形	Unicode	VS	90字形 CID
155	6762	寵	U+7AC8	E0101	20285	寵	U+7AC8	E0100	5937
156	6807	筵	U+7B75	E0101	20266	筵	U+7B75	E0100	5976
157	6832	籌	U+7BDD	E0101	7997	籌	U+7BDD	E0100	6001
158	7107	腱	U+8171	E0101	20275	腱	U+8171	E0100	6258
159	7159	艘	U+8258	E0101	14196	艘	U+8258	E0100	6310
160	7174	芒	U+8292	E0101	20292	芒	U+8292	E0100	6325
161	7342	虔	U+8654	E0101	20274	虔	U+8654	E0100	6481
162	7371	蜃	U+8703	E0101	20296	蜃	U+8703	E0100	6510
163	7404	蠅	U+8805	E0102	20295	蠅	U+8805	E0100	6537
164	7535	訝	U+8A1D	E0102	20268	訝	U+8A1D	E0100	6662
165	8043	靄	U+9744	E0100	7140	一	—	—	—
166	8055	靱	U+9771	E0102	13624	靱	U+9771	E0100	7152
167	8157	騙	U+9A19	E0101	8003	騙	U+9A19	E0100	7248
168	8277	鴉	U+9D09	E0101	14272	鴉	U+9D09	E0100	7362

注) 90字形で表記なしは04字形と同じであることを示す

注) みんなの文字ゴシックのデザインポリシーにより04字形と90字形が同じものがあります